

Installing & Configuring aACE

Last Modified on 07/26/2022 1:17 pm EDT

This guide explains how to install and configure aACE. It is intended for system administrators.

Install aACE on the Server

1. Download and extract the ZIP archive containing your aACE system.
2. At the FileMaker Pro initial dialog, use the menu to select **File > Sharing > Upload to Host**.
3. Select **127.0.0.1**, then enter the Admin Console login credentials, mark the flag to 'Save password in Keychain Access', and click **Sign In**.
4. At the Upload to Host dialog, click the **Change** button.
5. Make sure the **Databases** folder is highlighted, then click **New Folder**.
6. Name the new sub-folder "aACE 6", then click **OK**.
7. At the Upload to Host dialog again, click the **Browse** button, locate and select all the extracted aACE files, then click **Open**.
8. After the files are ready, click **Upload**.
9. After the upload is complete, click **Done**.

Note: Sometimes FileMaker will not upload some of the selected files. This is a known issue and does *not* indicate file corruption. If this happens, simply note which files still remain to be uploaded and run through the upload process again until all aACE files have uploaded successfully.

Please note that if you are installing any non-aACE files onto your aACE server, there is a possibility that these additional files may not open on FileMaker Server due to a lack of proper password protection. In the event that this happens and you must host these additional files, first enter the following command into the command line interface to allow non-protected files to be opened by FMS.

```
fmsadmin set serverconfig securefilesonly=false
```

Configure aACE Script Schedules

1. In the FileMaker Server Admin Console, navigate to **Configuration > Script Schedules**.
2. Set up the aACE 6 Automation Cycle A-G script schedules:
 - A. Click **Create Schedule** and enter these details:

- Schedule Type: FileMaker Script
 - Schedule Name: aACE 6 Automation Cycle A
 - Database:
 - Databases: aACEvXvX_Scripts.fmp12
 - Select the radial button for Account Name and Password
 - Account Name: management
 - Password: Use the associated management password assigned by aACEsoft.
 - Click outside the dialog to close it.
 - FileMaker Script:
 - Scripts: Automation Cycle
 - Mark the flag for Timeout (minutes).
 - Minutes: 120
 - Mark the flag to 'End the schedule if the timeout is reached'.
 - Click outside the dialog to close it.
 - Repeat:
 - Frequency: Daily
 - Start Date: Current date.
 - Time:
 - Change "At" to "Between"
 - Set the first time to "00:00"
 - Set the second time to "23:14"
 - Repeat Every: 1 Minutes
 - Do *not* set an end date.
 - Click outside the dialog, then click **Save**.
- B. Disable the schedule, mark the selection flag for it, then click **Duplicate** six times.
- C. On each duplicate:
- Click the Settings link and click Edit.
 - Change the Schedule Names to: "aACE 6 Automation Cycle B", "aACE 6 Automation Cycle C", "aACE 6 Automation Cycle D", "aACE 6 Automation Cycle E", "aACE 6 Automation Cycle F", and "aACE 6 Automation Cycle G".
- D. Enable all 7 schedules.
- E. Verify that each automation schedule runs and ends (i.e. the Scheduled Time updates to the next minute).
3. Set up the aACE 6 Automation HALT script schedule by disabling an existing schedule, duplicating it, and re-enabling it.
4. Edit the settings for the new schedule as follows:
- Schedule Name: aACE 6 Automation HALT
 - FileMaker Script: Automation HALT

- Repeat > Frequency: Once

5. Confirm that aACE 6 Automation HALT stays *disabled*.

Note: This schedule will never be enabled; it is only run manually by a user when necessary.

6. Confirm that aACE 6 Automation Cycle A, Cycle B, Cycle C, Cycle D, Cycle E, Cycle F, and Cycle G are all *enabled*.

7. If you are upgrading from a previous version of FMS and your previous configuration included custom automation schedules, recreate those custom schedules now.