

Clearing Saved Login Credentials

Last Modified on 12/30/2022 2:27 pm EST

This guide explains how to troubleshoot when old login credentials are preventing a new user from accessing aACE. It is intended for general users.

When a new employee will be using a previous team member's account for accessing aACE, the workstation used may cause difficulties. If that computer has stored the old login credentials, FileMaker may use this info to auto-login with the old account.

You can resolve this trouble during the login process or by manually clearing stored credentials. The steps for resolving this issue depend on how exactly you are accessing aACE:

- Using a Launcher — Follow *only* the instructions below for Manually Clearing Stored Credentials. (Using the shift-click method explained below on a launcher file will *not* work.)
- Using 'Show Hosts' in FileMaker — Follow either the instructions below for Interrupting the Automatic Login Process or for Manually Clearing Stored Credentials.

Interrupting the Automatic Login Process

When you access aACE as a local file set, you can use the keyboard to force the login dialog to display and to enter new user credentials.


- **Mac** — Double-click the fmp12 file, then immediately press and hold the **Option** key. At the login dialog, enter the new credentials. If you mark the flag to 'Save password in Keychain Access', these new credentials will become the default FileMaker user account on the workstation.
- **PC** — Hold down the **Shift** key as you double-click the fmp12 file. At the login dialog, enter the new credentials. If you mark the flag to 'Save password in Credential Manager', these new credentials will become the default FileMaker user account on the workstation.

Manually Clearing Stored Credentials

When you access aACE with a launcher, use the following steps for Mac or PC to remove the previous user's login credentials.

Mac


1. In the Finder list of Applications, double-click **Utilities**, then double-click **Keychain Access**.
2. In the Keychains used for **login**, click the column heading **Kind** to sort the list.



3. Scroll through the list to locate the credentials with the Kind noted as "**FileMaker...**" passwords.
4. Find the entry named "aACE" or "aACEv6v0", right-click it (or Control+click), and select **Delete...**
5. At the confirmation dialog, click **Delete**.
The next time you access aACE, the login dialog will display.

PC

1. Click the Windows icon / Start button, then type "**Credential Manager**" in the search field and press **Enter**.
2. On the Credential Manager initial screen, click **Windows Credentials**.
3. In the list of Generic Credentials, find the entry named "FMP: aACE" or "FMP: aACEv6v0", click the down arrow for that line to expand the details, then click **Remove**.



4. At the confirmation dialog, click **Yes**.
The next time you access aACE, the FileMaker login dialog will display.